CALL SIGN FORMATION POSSIBILITIES
(see Section III of Article **19**)

Type of station	RR number	Permitted formations	Number* of combinations	Observations
Fixed stations	**19.52**	XXA-XXZ XXA2-XXZ9 XXA20-XXZ99 ¹ XXA200-XXZ999	26 208 2 080 20 800	¹ Recommended, as far as possible (see RR **19.53**)
Land stations	**19.52**	XXA-XXZ XXA2-XXZ9 XXA20-XXZ99 ¹ XXA200-XXZ999	26 208 2 080 20 800	
Ship stations	**19.55**	XXAA-XXZZ XXAA2-XXZZ9 X**L**2000-X**L**9999 XXA2000-XXZ9999	676 5 408 8 000 208 000	**L** = Second character is a letter
Ship's survival craft stations	**19.60**	**P**00-**P**99 ** **P**20-**P**99 ***	100 per ship 80 per ship	**P** = Call sign of the parent ship (see RR **19.55 - 19.56**)
EPIRB stations	**19.62**	**B** **P** **BP**	no limit	**B** = Morse letter B **P** = Call sign of the parent ship (see RR **19.55 - 19.56**)
Aircraft stations	**19.58**	XXAAA-XXZZZ	17 576	
Aircraft survival craft stations	**19.64**	**P**2-**P**9	8 per aircraft	**P** = The complete call sign of the parent aircraft (see RR **19.58**)
Land mobile stations	**19.66**	X**L**2000-X**L**9999 XXA2000-XXZ9999 XXAA2000-XXZZ9999	8 000 208 000 5 408 000	**L** = Second character, provided it is a letter
Amateur stations	**19.68** **19.68A** **19.69**	**Y**0A-**Y**9Z **Y**0XA-**Y**9XZ **Y**0XXA-**Y**9XXZ **Y**0XXXA-**Y**9XXXZ	260 6 760 175 760 4569 760	**Y** = First character, provided that it is the letter B, F, G, I, K, M, N, R or W (see RR 19.68)
		XX0A-XX9Z XX0XA-XX9XZ XX0XXA-XX9XXZ XX0XXXA-XX9XXXZ	260 6 760 175 760 4569 760	
	19.68.1	XXX0A-XXX9Z XXX0XA-XXX9XZ XXX0XXA-XXX9XXZ	6 760 175 760 4569 760	These formation possibilities are valid only in case of half series (when the first two characters are allocated to more than one Member State)
Experimental stations	**19.68** **19.68A**	**Y**2A-**Y**9Z **Y**2XA-**Y**9XZ **Y**2XXA-**Y**9XXZ **Y**2XXXA-**Y**9XXXZ	208 5 408 140 608 3655 808	**Y** = First character, provided that it is the letter B, F, G, I, K, M, N, R or W (see RR 19.68)
		XX2A-XX9Z XX2XA-XX9XZ XX2XXA-XX9XXZ XX2XXXA-XX9XXXZ	208 5 408 140 608 3655 808	
Stations in the space service	**19.71**	XX00-XX99 XX000-XX999	100 1 000	If second character is a digit
		XX20-XX99 XX200-XX999	80 800	If second character is a letter

XX = First two characters of allocated call sign series.
*   = The actual number may be less, in order to comply with RR **19.46 - 19.48.**
**   = If last character of **P** is a digit.
*** = If last character of **P** is a letter.